

Soundiation: User Manual

Last update: January 11, 2022


Contact: Tianquan Tang (tianquan@connect.hku.hk)

- *Soundiation* runs on Microsoft Windows with MATLAB 2010a or above versions installed.
- *Soundiation* supports parallel computation:
 - Parallel computation greatly reduces computational time, depended on the cores number of computer.
 - To enable parallel computation, we need to activate MATLAB parallel pool by simply typing

```
>> matlabpool;           % for MATLAB 2010a
```

or

```
>> parpool;
```

on Command Window before running the GUI.
- Start *Soundiation* in MATLAB:
 - Set the Current Folder direction to “.\Soundiation\src”:or type


```
>> addpath('<folderpath>\Soundiation\src');
```

on Command Window to open the interface.
 - Type

```
>> main_interface;
```

on Command Window to open the interface.

➤ Main interface



2. Parametric control panel

3. Functional panel and Control panel

➤ Result visualization panel

Figure 1:
Visualize the levitated particle.

Figure 2:
Visualize the position relationship between transducer array and the levitated particle.
(If **Transducer array (circular oscillator)** feature is selected)

Figure 4 to Figure 9:
Visualize the time-variation position and orientation.
(If **Transducer array (circular oscillator)** feature is selected)




Figure adjustment and data collection

Figure 3:
Visualize incident pressure wavefield.

Figure 10:
Visualize the time-variation trajectory. The solid line and the arrows indicate the translational and rotational motions, respectively.
(If **Transducer array (circular oscillator)** feature is selected)

➤ Parametric control panel (Overall)

Particle parameters:
Define the particle physical properties.

Boundary conditions:
Define the boundary condition of the particle.

Medium parameters:
Define the medium physical properties.

Calculation controls

Particle parameters

NOTE: if averaged radius changed, we have to re-select GEOs again.

Ellipsoidal particle

Cn [0.002 0 0.0004]

Particle density 15 kg/m³

Averaged radius 0.002 m

Initial position [0.002 0 0] m

Initial orientation [0 0 0] rad

Particle visualization

Boundary conditions

B.C. (default: Sound-hard)

Host-fluid parameters

Medium (default: Air)

Fluid density 1.224 kg/m³

Speed of sound 340 m/s

Dynamic viscosity 0.0000185 Pa s

Wavefront parameters

Frequency 40000 Hz

Integration radius 0.005 m

Transducer array (circular osci...)

Controls: plane-type wavefront

Pressure (amp) 1 Pa

Controls: transducer array

Transducer number 2

Transducer radius 0.005 m

Radial velocity (amp) 1.5 m/s

Interdistance 0.02 m

Transducer positions [0 0 0; 0.01 0 0] m

Phase delay [0 0] rad

Relative amplitude delay [1 1]

Transducer visualization

Wavefield (xOz plane)

Wavefront parameters:
Define the incident wavefield.

➤ Parametric control panel (Particle & Medium parameters, and B.C.)

Particle parameters

NOTE: if averaged radius changed, we have to re-select GEOs again.

Ellipsoidal particle

Cn [0.002 0 0.0004]

Particle density 15 kg/m³

Averaged radius 0.002 m

Initial position [0.002 0 0] m

Initial orientation [0 0 0] rad

Particle visualization

Visualize the geometry based on "Particle parameters" in **Figure 1** of "Result visualization panel"; at the same time, the particle geometric data is created and saved in "*particle_data.stl*", which can be directly imported to **COMSOL** for further numerical calculations.

Geometries (default: Spherical)

Geometries (default: Spherical)






Spherical particle

Ellipsoidal particle

Cone particle

Diamond particle

Others (user-specified 'Cn')



User-specified mapping coefficient:
Cn = [0.002 0 -0.0005 0 -0.00025]

Boundary conditions

B.C. (default: Sound-hard)

B.C. (default: Sound-hard)

Host-fluid

Sound-hard B.C.

Sound-soft B.C.

Boundary conditions:

there are two common options, *sound-hard* (Neumann) and *sound-soft* (Dirichlet) conditions.

Host-fluid parameters

Medium (default: Air)

Medium (default: Air)

Fluid

Air

Water

Speed of sound 340 m/s

Dynamic viscosity 0.0000185 Pa s

Medium:

there are two common options, *air* and *water* medium.

The medium properties are automatically implanted once the "Medium popup menu" is selected.

Cn: geometric mapping coefficients;
(The 'Cn' of four typical geometries of *spherical*, *ellipsoidal*, *cone*, and *diamond* particles are provided. User can also *self-specify* the 'Cn' for more complex geometries)

Initial position&orientation: define the initial position of mass center of particle deviated from origin of Cartesian coordinates;
the initial angle between symmetric axis of particle and *x*-, *y*-, and *z*-axes.

➤ Parametric control panel (Wavefront parameters)

Wavefront parameters

Frequency

40000

Hz

Integration radius

0.005

m

Transducer array (circular osci...

▼

Frequency: set the operating frequency of incident wave.

Integration radius: define the spherical space that the acoustic fields are approximated by partial-wave expansion series;
(we found “*integration radius* ≈ 0.005 m” can get a high accurate radiation force and torque through validating with the full three-dimensional numerical simulations in COMSOL)

Transducer positions

[0 0 0; 0.01 0 0]

m

Phase delay

[0 0]

rad

Relative amplitude delay

[1 1]

Visualize the acoustic pressure field in Figure 3 of “Result visualization panel”.

Wavefield (xOz plane)

Wavefront (default: Plane wave) ▼

Wavefront (default: Plane wave)

Plane travelling wave

Transducer array (circular oscillator)

Controls: plane-type wavefront

Pressure (amp)

1

Pa

Pressure (amp): set the pressure amplitude of the incident plane wave.
(ONLY activated when the “Wavefront popup menu” selects Plane travelling wave feature)

Controls: transducer array

Transducer number

2

Transducer radius

0.005

m

Radial velocity (amp)

1.5

m/s

Interdistance

0.02

m

Transducer positions

[0 0 0; 0.01 0 0]

m

Phase delay

[0 0]

rad

Relative amplitude delay

[1 1]

Transducer visualization

Radial velocity (amp): set the radial vibration amplitude of the circular oscillator of the transducers.

Interdistance: set the initial vertical distance between the coordinate origin and transducer array.

Transducer positions: set the initial positions of transducer. Each row gives the x-, y-, and z-positions of a transducer.

Phase&Relative amplitude delay: set the phase and amplitude parameters of the transducer array.
(The above parameters ONLY activated when the “Wavefront popup menu” selects Transducer array (circular oscillator) feature)

Visualize the particle-transducer system based on “Particle parameters” and “Controls: Transducer array” parameters in Figure 2 of “Result visualization panel”.

2

z-axis [mm]

20

0

-20

-40

-60

10

0

-10

10

y-axis [mm]

x-axis [mm]

om 3 tional coordinates (xOz Plane)

0.02

0.01

0

-0.01

-0.02

500

0

-500

-0.01

0

0.01

x-axis [m]

z-axis [m]

➤ Functional panel and Control panel

**Prediction of the radiation
force and torque**

**Calculation the acoustophoretic
process of the particle**

Functions

Radiation force and torque

Radiation force N

Radiation torque N m

Calculation

Acoustophoresis for transducer array ONLY

Time step s ; Ending time s

Current calculated for time s

Calculation Data saved in:

Controls

Select saved figure: Save figure Reset Reset and Exit

**Save figures and Reset
parameters to default values**

➤ Functional panel

Radiation force and torque

Radiation force [-7.3206e-008 8.2886e-020 2.6585e-006] N

Radiation torque [5.3267e-022 3.7968e-010 -5.9868e-023] N·m

Calculation

Present the predicted radiation force and torque:

Radiation force = [-7.3206e-008 8.2886e-020 2.6585e-006] N,

Radiation torque = [5.3267e-022 3.7968e-010 -5.9868e-023] N·m;

i.e.,

$$\begin{cases} F_{\text{rad},x} = -7.3206 \times 10^{-8} \text{ N} \\ F_{\text{rad},y} = +8.2886 \times 10^{-20} \text{ N} \\ F_{\text{rad},z} = +2.6585 \times 10^{-8} \text{ N} \end{cases} \text{ and } \begin{cases} T_{\text{rad},x} = +5.3267 \times 10^{-22} \text{ N} \cdot \text{m} \\ T_{\text{rad},y} = +3.7968 \times 10^{-10} \text{ N} \cdot \text{m} \\ T_{\text{rad},z} = -5.9868 \times 10^{-23} \text{ N} \cdot \text{m} \end{cases}$$

Click on the “Calculation” button to predict the radiation force and torque.

Acoustophoresis for transducer array ONLY

Time step 0.0001 s; Ending time 0.1 s

Current calculated for time 0.0033 s

Calculation Data saved in: MyFilename.txt

Click on the “Calculation” button to start the acoustophoretic prediction.

Time step: set the time step for iterative calculation of the particle dynamics.

Ending time: set the ending moment.


Current calculated for time: indicate the progress of the calculation.

Data saved in: specify the fold direction to save the data of the particle position and orientation at different moments in file “MyFilename.txt”.


Note: when the vertical distance between the mass center of particle and transducer array (i.e., the interdistance) small than 0.01 mm, we stop the dynamic calculation and regard the particle cannot be trapped.

(The above parameters **ONLY** activated when the “Wavefront popup menu” selects **Transducer array (circular oscillator)** feature)

➤ Control panel (Save figures, Reset and Exit)



After clicking on the “Save figure” button, a new window will present. The user need to specify a filename and format to save the selected figure. The software supports ‘*.jpeg’, ‘*.png’, ‘*.tiff’, and ‘*.eps’ formats.



➤ Template: saved data of particle acoustophoresis (MyFilename.txt)

```
1 %Computational parameters
2
3 Geometry = Ellipsoidal particle;
4     Cn = [0.002      0      0.0004];
5     Particle density = 15 [kg/m^3];
6     Particle radius = 0.002 [m];
7     Initial position = [0.002 0 0] [m];
8     Initial orientation = [0 0 0] [rad];
9
10 Boundary condition = B.C. (default: Sound-hard);
11
12 Medium = Medium (default: Air);
13     Fluid density = 1.224 [kg/m^3];
14     Fluid sound speed = 340 [m/s];
15     Fluid dynamic viscosity = 0.0000185 [Pa s];
16
17 Wave type = Transducer array (circular oscillator);
18     Frequency = 40000 [Hz];
19     Integration radius = 0.005 [m];
20     Transducer number = 2;
21     Transducer radius = 0.005 [m];
22     Transducer vibration radial velocity = 1.5 [m/s];
23     Interdistance between the particle and the array = 0.02 [m];
24     Transducer position matrix = [0 0 0; 0.01 0 0] [m];
25     Transducer phase delay = [0 0] [rad];
26     Transducer relative amplitude delay = [1 1];
27
28
29
```

Parameters saved in “MyFilename.txt”:
the saved computational parameters, including the particle parameters, the boundary condition, the medium parameters, and the wavefront parameters.

➤ Template: saved data of particle acoustophoresis (MyFilename.txt)

```
30 %Dynamic data:
31
32 Time [ms]      X_position [m]      Y_position [m]      Z_position [m]      X_angle [rad]      Y_angle [rad]      Z_angle [rad]
33 0.000000      0.002000      0.000000      0.000000      0.000000      0.000000      0.000000
34 0.100000      0.001990      0.000000      -0.000325      0.000000      0.010207      -0.000000
35 0.200000      0.001976      0.000000      -0.000642      0.000000      0.022184      -0.000000
36 0.300000      0.001959      0.000000      -0.000952      0.000000      0.036192      -0.000000
37 0.400000      0.001938      0.000000      -0.001255      0.000000      0.052507      -0.000000
38 0.500000      0.001913      0.000000      -0.001550      0.000000      0.071411      -0.000000
39 0.600000      0.001883      0.000000      -0.001840      0.000000      0.093175      -0.000000
40 0.700000      0.001847      0.000000      -0.002123      0.000000      0.118038      -0.000000
41 0.800000      0.001806      0.000000      -0.002401      0.000000      0.146180      -0.000000
42 0.900000      0.001759      0.000000      -0.002672      0.000000      0.177683      -0.000000
43 1.000000      0.001707      0.000000      -0.002938      0.000000      0.212502      -0.000000
44 1.100000      0.001649      0.000000      -0.003198      0.000000      0.250422      -0.000000
45 1.200000      0.001586      0.000000      -0.003451      0.000000      0.291036      -0.000000
46 1.300000      0.001521      0.000000      -0.003696      -0.000000      0.333745      -0.000000
47 1.400000      0.001455      0.000000      -0.003932      -0.000000      0.377769      -0.000000
48 1.500000      0.001389      0.000000      -0.004158      -0.000000      0.422205      -0.000000
49 1.600000      0.001328      0.000000      -0.004375      -0.000000      0.466098      -0.000000
50 1.700000      0.001272      0.000000      -0.004582      -0.000000      0.508538      -0.000000
51 1.800000      0.001223      0.000000      -0.004780      -0.000000      0.548753      -0.000000
52 1.900000      0.001182      0.000000      -0.004971      -0.000000      0.586172      -0.000000
53 2.000000      0.001150      0.000000      -0.005155      -0.000000      0.620451      -0.000000
54 2.100000      0.001127      0.000000      -0.005336      -0.000000      0.651449      -0.000000
55 2.200000      0.001112      0.000000      -0.005513      -0.000000      0.679183      -0.000000
56 2.300000      0.001105      0.000000      -0.005689      -0.000000      0.703768      -0.000000
57 2.400000      0.001106      0.000000      -0.005863      -0.000000      0.725379      -0.000000
58 2.500000      0.001112      0.000000      -0.006038      -0.000000      0.744217      -0.000000
59 2.600000      0.001124      0.000000      -0.006214      -0.000000      0.760493      -0.000000
60 2.700000      0.001141      0.000000      -0.006392      -0.000000      0.774424      -0.000000
61 2.800000      0.001162      0.000000      -0.006574      -0.000000      0.786230      -0.000000
62 2.900000      0.001186      0.000000      -0.006760      -0.000000      0.796141      -0.000000
63 3.000000      0.001213      0.000000      -0.006954      -0.000000      0.804413      -0.000000
64 3.100000      0.001241      0.000000      -0.007156      -0.000000      0.811333      -0.000000
65 3.200000      0.001270      0.000000      -0.007368      -0.000000      0.817254      -0.000000
66 3.300000      0.001301      0.000000      -0.007594      -0.000000      0.822613      -0.000000
67 3.400000      0.001331      0.000000      -0.007833      -0.000000      0.827991      -0.000000
```

Time-variant data saved in “MyFilename.txt”:
the saved position and orientation data of the particle in different moments.